Python Scripts for NIED continuous waveform data requesting and processing

• Author: Dongdong Tian @ USTC

• Update: 2015-01-17

This is a collection of scripts to request, download and process continuous waveform data available from NIED Hi-net website.

It does not come with any warranties, nor is it guaranteed to work on your computer. The user assumes full responsibility for the use of all scripts. The author is **NOT** responsible for any damage that may follow from correct *or* incorrect use of these scripts.

Dependency

- Python 3.4 (Not work under Python 2; Not Tested under Python 3.3)
- Python third-party modules
 - requests
 - clint
 - docopt
- Hinet win32tools: catwin32 and win2sac_32

How to get

If you use git, just clone this repo to your work directory:

```
git clone https://github.com/seisman/HinetScripts.git
```

You can update this repo using:

git pull

If you do not use git, just click the "Download ZIP" button on the right.

Before you use it

1. Register on the NIED Hi-net website, so you can access to NIED waveform data;

- 2. Download win32tools and compile them, make sure binary catwin32 and win2sac_32 are in you PATH;
- 3. Request, download and process data manually at least one time, make sure that you know the whole procedures and limitations of NIED website;
- 4. Modify configure file Hinet.cfg to your needs:
- User & Password
- Net: Network code to request waveform data as default
- Maxspan: Maximum record length allowed for one web request
- catwin32: Path to catwin32 supplied by win32tools
- 4. Run HinetDoctor.py to check your configure file;

What is network code?

Each network is represented by a network code. For example, Hi-net network has a code of '0101', while V-net '0105'. You can see the full code list by run python HinetContRequest.py -h.

What is Maxspan? And how to choose it?

NIED Hi-net website set a limitation of data size in one request:

- 1. Record Length < 60 min
- 2. Number of channels * Record Length <= 12000 min

Just take Hi-net as example, Hi-net network has about 800 station and 24000 channels. According to the limitations, the record length should be no more than 5 minutes long in one web request. So the Maxspan, allowed maximum record length, should be no more than 5 for Hi-net network with all stations selected.

The request script HinetContRequest.py helps you break through the limitation. Using this script, you can requst datas with a much longer record length, this script will split the request into multiple sub-request, each has a record length no more than Maxspan minutes.

Quick Start

If you want a quick start, just run like this:

```
$ python HinetContRequest.py 2010 10 01 15 00 20 -d 201010010600
```

- \$ python rdhinet.py 201010010600
- \$ python ch2pz.py 201010010600

if everything goes right, you will have one cnt file, one channel table file, several SAC files and SAC polezero files in directory.

Scripts

HinetDoctor.py

HinetDoctor.py helps you check your configure file, you should run it when you modify Hinet.cfg.

- 1. Is username and password correct?
- 2. Has Hi-net website been updated?
- 3. Is catwin32 command in you path and executable?
- 4. How many station are selected for Hi-net and F-net?
- 5. Is Maxspan in allowed range?

HinetContRequest.py

HinetContRequest.py is used to request and download data from Hi-net server.

Usage

```
$ python HinetContRequest.py -h
Request continuous waveform data from NIED Hi-net.
```

Usage:

```
HinetContRequest.py <year> <month> <day> <hour> <min> <span> [options]
HinetContRequest.py -h
```

Options:

```
-h, --help Show this help.

-c CODE --code=CODE Select code for organization and network.

-m SPAN --maxspan=SPAN Max time span for sub-requests

-d DIR --directory=DIR Output directory. Default: current directory.

-o FILE --output=FILE Output filename.

-t FILE --ctable=FILE Channel table filename. Default: CODE_YYYYMMDD.ch
```

Examples

1. Request data of Hi-net start from 2010-10-01T15:00:00 (JST) with duration of 20 minutes

```
python HinetContRequest.py 2010 10 01 15 00 20
```

2. Request data of F-net start from 2010-10-01T15:00:00 (JST) with duration of 20 minutes

```
python HinetContRequest.py 2010 10 01 15 00 20 -c 0103
```

3. Request data of Hi-net, with customized output directory and filename

```
python HinetContRequest.py 2010 10 01 15 00 20 -d aaa -o aaa.cnt -t aaa.ch
```

4. Request data of Hi-net, use default filename and customized output directory. (**Highly Recommended**)

```
python HinetContRequest.py 2010 10 01 15 00 20 -d 201010010600
```

If you run HinetContRequest.py in the highly recommender way, you will get a directory 201010010600 with two file inside: 0101_201010011500_20.cnt and 0101_20101001.ch.

```
|-- 201010010600
|-- 0101_201010011500_20.cnt
`-- 0101_20101001.ch
```

rdhinet.py

rdhinet.py is used to extract SAC files from WIN32 file.

Usage

Extract SAC data files from NIED Hi-net WIN32 files

Usage:

```
rdhinet.py DIRNAME [-C <comps>] [-D <outdir>] [-S <suffix>] [-P procs>]
rdhinet.py -h
```

Options:

-h Show this help.

- -S <suffix> Suffix of output SAC files. Default: no suffix.

Examples

1. Extract all channels

```
python rdhinet.py 201010010600
```

2. Extract NEU components with suffix 'SAC'

```
python rdhinet.py 201010010600 -C U,N,E -S SAC
```

In most cases, what you need is only -C option.

If you run python rdhinet.py 201010010600 -C U, you will get SAC files looks like N.FRNH.U under directory 201010010600.

ch2py.py

ch2pz.py is used to extract SAC PZ files from Channel Table file.

Usage

```
$ python ch2pz.py -h
Convert NIED Hi-net Channel Table file to SAC PZ files
```

Usage:

```
ch2pz.py DIRNAME [-C <comps>] [-D <outdir>] [-S <suffix>]
```

Options:

-S <suffix> Suffix for SAC PZ files. [default: SAC_PZ]

Examples

1. Extract all channels

```
python ch2pz.py 201010010600
```

2. Extract NEU components

```
python ch2pz.py 201010010600 -C U,N,E
```

In most cases, what you need is only $-\mathtt{C}$ option.

If you run python ch2pz.py 201010010600 -C U, you will get SAC PoleZero files looks like N.FRNH.U.SAC_PZ under directory 201010010600.

Attentions

- ch2pz.py only works for components whose input have unit of ${\tt m/s}.$