Python Scripts for NIED continuous waveform data requesting and processing

• Author: Dongdong Tian @ USTC

• Update: 2015-05-29

This is a collection of scripts to request, download and process continuous waveform data available from NIED Hi-net website.

It does not come with any warranties, nor is it guaranteed to work on your computer. The user assumes full responsibility for the use of all scripts. The author is **NOT** responsible for any damage that may follow from correct *or* incorrect use of these scripts.

Dependency

- Python 3.4 (Not work under Python 2; Not Tested under Python 3.3)
- Python third-party modules
 - requests
 - clint
 - docopt
- Hinet win32tools: catwin32 and win2sac_32 in your PATH

How to get

If you use git, just clone it to your working directory:

```
git clone https://github.com/seisman/HinetScripts.git
```

After git clone, you can get the latest version anytime with just one command:

git pull

If you do not use git, just click the "Download ZIP" button on the right.

Before you use it

- 1. Make sure you have Python 3.4
- 2. Install Python third-party modules by pip install -r requirements.txt

- 3. Register on the NIED Hi-net website, so you have access to NIED waveform data:
- 4. Download win32tools and compile them, make sure binary catwin32 and win2sac 32 are in you PATH;
- 5. Request, download and process data manually at least one time, make sure that you know the whole procedures and limitations of NIED website;
- 6. Modify configure file Hinet.cfg to your needs:
- User and Password
- Net: Network code to request waveform data as default
- Maxspan: Maximum record length allowed for one web request
- 7. Run HinetDoctor.py to check your configure file;

If you can read Chinese, posts listed here may help you understand details.

What is network code?

Each network is represented by a network code. For example, Hi-net network has a code of '0101', while V-net '0105'. You can see the full code list by run python HinetContRequest.py -h.

What is Maxspan? And how to choose it?

NIED Hi-net website set a limitation of data size in one request:

- 1. Record Length < 60 min
- 2. Number of channels * Record Length <= 12000 min

Just take Hi-net as example, Hi-net network has about 800 station and 24000 channels. According to the limitations, the record length should be no more than 5 minutes long in one web request. So the Maxspan, allowed maximum record length, should be no more than 5 for Hi-net network with all stations selected.

The request script HinetContRequest.py helps you break through the limitation. Using this script, you can requst datas with a much longer record length, this script will split the request into multiple sub-requests, each has a record length no more than Maxspan minutes.

Quick Start

If you want a quick start, just run like this, commands below will request waveform data from 2010:10:01T15:20:00(+0900) to 2010:10:01T15:20:00(+0900):

```
$ python HinetDoctor.py
$ python HinetContRequest.py 2010 10 01 15 00 20 -d 201010010600
$ python rdhinet.py 201010010600
$ python ch2pz.py 201010010600
```

if everything goes right, you will have one cnt file, one channel table file, several SAC files and SAC polezero files under directory 201010010600.

Scripts

HinetDoctor.py

HinetDoctor.py helps you check your configure file, you should run it everytime after you modify Hinet.cfg.

- 1. Is username and password correct?
- 2. Has Hi-net website been updated?
- 3. Are catwin32 and win2sac_32 in PATH and executable?
- 4. How many stations are selected for Hi-net and F-net?
- 5. Is Maxspan in allowed range?

StationSelector.py

StationSelector.py is used to select stations you want to request data.

Usage

```
Select Hi-net/F-net stations to request waveform data from NIED
```

Usage:

```
StationSelector.py -c CODE [-1 LIST] StationSelector.py -h
```

Options:

```
-h, --help Show this help.
-c CODE, --code=CODE Network code. Hi-net: 0101, F-net: 0103.
-l LIST, --list=LIST Station list file.
```

Notes

- 1. You can only select station of Hi-net or F-net.
- 2. All stations will be selected if -l options is NOT used.
- 3. List file contains station list, one station per line, lines start with '#' will be ignored.
- 4. This script does NOT check whether a station belongs to a network.
- 5. You may need to run HinetDoctor.py again to check your station selection.

Examples

- 1. Select all stations of Hi-net
 - \$ python StationSelector.py -c 0101
- 2. Select several stations list in a file:

```
$ cat sta.list
```

N.FJ2H

N.OTWH

N.IICH

N.SMGH

\$ python StationSelector.py -c 0101 -l sta.list

HinetContRequest.py

HinetContRequest.py is used to request and download data from NIED server.

Usage

```
$ python HinetContRequest.py -h
Request continuous waveform data from NIED Hi-net.
```

Usage:

```
HinetContRequest.py <year> <month> <day> <hour> <min> <span> [options]
HinetContRequest.py -h
```

Options:

```
-h, --help Show this help.
-c CODE --code=CODE Select code for organization and network.
-m SPAN --maxspan=SPAN Max time span for sub-requests
-d DIR --directory=DIR Output directory. Default: current directory.
-o FILE --output=FILE Output filename.
-t FILE --ctable=FILE Channel table filename. Default: CODE_YYYYMMDD.ch
```

Examples

1. Request data of Hi-net start from 2010-10-01T15:00:00 (JST) with duration of 20 minutes

```
python HinetContRequest.py 2010 10 01 15 00 20
```

2. Request data of F-net start from 2010-10-01T15:00:00 (JST) with duration of 20 minutes

```
python HinetContRequest.py 2010 10 01 15 00 20 -c 0103
```

3. Request data of Hi-net, use default filename and customized output directory. (**Highly Recommended**)

```
python HinetContRequest.py 2010 10 01 15 00 20 -d 201010010600
```

4. Request data of Hi-net, with customized output directory and filename

```
python HinetContRequest.py 2010 10 01 15 00 20 -d aaa -o aaa.cnt -t aaa.ch
```

WARNING Although this script supports customized output filenames, you should never use -o and -t options, because the cnt filename and channel table filename are hard coded in rdhinet.py and ch2pz.py.

If you run HinetContRequest.py in the highly recommender way, you will get a directory 201010010600 with two file inside: 0101_201010011500_20.cnt and 0101_20101001.ch.

```
|-- 201010010600
|-- 0101_201010011500_20.cnt
`-- 0101_20101001.ch
```

rdhinet.py

rdhinet.py is used to extract SAC files from WIN32 file.

Usage

Extract SAC data files from NIED Hi-net WIN32 files

Usage:

rdhinet.py DIRNAME [-C <comps>] [-D <outdir>] [-S <suffix>] [-P procs>]
rdhinet.py -h

Options:

- -h Show this help.
- -C <comps> Components to extract, delimited using commas.

Avaiable components are U, N, E, X, Y et al.

Default to extract all components.

- -D <outdir> Output directory for SAC files.
- -S <suffix> Suffix of output SAC files. Default: no suffix.
- -P procs> Parallel using multiple processes.

Set number of CPUs to cprocs> if cprocs> equals 0. [default: 0]

Examples

1. Extract all channels

python rdhinet.py 201010010600

2. Extract NEU components with suffix 'SAC'

```
python rdhinet.py 201010010600 -C U,N,E -S SAC
```

In most cases, what you need is only -C option.

If you run python rdhinet.py 201010010600 -C U, you will get SAC files looks like N.FRNH.U under directory 201010010600.

ch2py.py

ch2pz.py is used to extract SAC PZ files from Channel Table file.

Usage

\$ python ch2pz.py -h
Convert NIED Hi-net Channel Table file to SAC PZ files

Usage:

```
ch2pz.py DIRNAME [-C <comps>] [-D <outdir>] [-S <suffix>]
```

Options:

```
-C <comps> Channel Components to convert. Choose from U,N,E,X,Y et. al.
    Default to convert all components.
-D <outdir> Output directory of SAC PZ files. Use the directory of
        Channel Table file as default.
-S <suffix> Suffix for SAC PZ files. [default: SAC_PZ]
```

Examples

1. Extract all channels

```
python ch2pz.py 201010010600
```

2. Extract NEU components

```
python ch2pz.py 201010010600 -C U,N,E
```

In most cases, what you need is only -C option.

If you run python ch2pz.py 201010010600 -C U, you will get SAC PoleZero files looks like N.FRNH.U.SAC_PZ under directory 201010010600.

Attentions

• ch2pz.py only works for components whose input have unit of m/s.